

# User Guide - Cigar Lounge Smoke Simulation Tool

---

## Table of Contents

---

1. [Getting Started](#)
  2. [User Interface Overview](#)
  3. [Running a Simulation](#)
  4. [Configuring Sensors](#)
  5. [Fan Control](#)
  6. [Interpreting Results](#)
  7. [Advanced Features](#)
- 

## Getting Started

---

### Installation

1. **Install Python 3.8+** (if not already installed)

```
bash
python3 --version # Check your Python version
```

2. **Install Dependencies**

```
bash
pip install -r requirements.txt
```

3. **Run the Application**

```
bash
python main.py
```

### First Time Setup

When you first launch the application:

1. You'll see a 3D view of the empty room on the left
  2. Control panels are below the 3D view
  3. Data displays and graphs are on the right side
- 

## User Interface Overview

---

### Main Window Layout

The application window is divided into two main sections:

#### Left Panel: 3D View and Controls

- **3D Visualization:** Shows the room, smoke particles, sensors, and fan
- Use mouse to rotate view (click and drag)

- Use mouse wheel to zoom in/out
- **Control Tabs:**
- **Simulation Tab:** Start/pause/reset, smoker count, simulation speed
- **Sensors Tab:** Add/remove sensor pairs and configure positions
- **Fan Control Tab:** Switch between manual/auto mode, set fan speed

## Right Panel: Data and Analysis

- **Data Tabs:**
  - **Sensor Readings:** Real-time PPM and clarity values for all sensors
  - **Graphs:** Time-series plots of PPM, clarity, and fan speed
  - **Statistics:** Summary statistics and export options
- 

# Running a Simulation

---

## Basic Workflow

### Step 1: Set Number of Smokers

1. Go to **Simulation** tab (bottom left)
2. Adjust “Number of Smokers” spinner (0-48)
3. Default is 24 smokers

### Step 2: Add Sensor Pairs (Optional but Recommended)

1. Go to **Sensors** tab
2. Set sensor configuration:
  - **Distance from Fan:** How far from the fan (in feet)
  - **Low Sensor Height:** Height of low sensor from floor
  - **High Sensor Height:** Height of high sensor from floor
3. Click “Add Sensor Pair”
4. Repeat to add up to 4 pairs

### Recommended Sensor Configurations:

- **Near-Fan Pair:** 10ft from fan, Low:3ft, High:12ft
- **Mid-Room Pair:** 35ft from fan, Low:3ft, High:12ft
- **Far Pair:** 60ft from fan, Low:3ft, High:12ft

### Step 3: Configure Fan Control

1. Go to **Fan Control** tab
2. Choose mode:
  - **Manual:** You control fan speed with slider
  - **Automatic:** Controller adjusts speed based on sensor readings
3. For Manual mode: Use slider to set desired fan speed (0-100%)

### Step 4: Start Simulation

1. Click **Start** button in Simulation tab
2. Watch the 3D view as smoke particles are generated and move
3. Monitor sensor readings in real-time on the right panel
4. Observe graphs updating automatically

## Step 5: Analyze Results

1. Switch to **Statistics** tab to see summary
  2. Look for:
    - Peak PPM values
    - Time to clear the room
    - Average air quality
  3. Export data to CSV for detailed analysis
- 

## Configuring Sensors

---

### Sensor Pair Concept

Each sensor pair consists of:

- **Low Sensor** (Green): Placed at breathing level (~3ft)
- **High Sensor** (Red): Placed near ceiling where smoke accumulates (~12ft)

### Placement Guidelines

#### Distance from Fan

- **Close (5-15ft)**: Detects smoke being drawn to fan
- **Medium (20-40ft)**: Monitors mid-room conditions
- **Far (45-65ft)**: Checks front of room (farthest from fan)

#### Height Guidelines

- **Low Sensor**: 2-4 feet (breathing/sitting level)
- **High Sensor**: 10-16 feet (smoke accumulation zone)
- **Minimum separation**: 2 feet between low and high

### Strategic Placement Examples

#### Configuration 1: Single Pair (Minimum)

- **Pair 1**: 30ft from fan, Low:3ft, High:12ft
- General room monitoring

#### Configuration 2: Three Pairs (Recommended)

- **Pair 1**: 15ft from fan, Low:3ft, High:12ft (Near fan)
- **Pair 2**: 35ft from fan, Low:3ft, High:12ft (Middle)
- **Pair 3**: 60ft from fan, Low:3ft, High:12ft (Far end)
- Provides comprehensive coverage

#### Configuration 3: Four Pairs (Maximum Coverage)

- **Pair 1**: 10ft from fan, Low:3ft, High:15ft
  - **Pair 2**: 25ft from fan, Low:3ft, High:12ft
  - **Pair 3**: 45ft from fan, Low:3ft, High:12ft
  - **Pair 4**: 65ft from fan, Low:3ft, High:10ft
  - Maximum spatial resolution
-

## Fan Control

---

### Manual Mode

In manual mode, you have direct control:

1. Select “Manual” from Fan Mode dropdown
2. Use the slider to set fan speed (0-100%)
3. Fan will ramp to target speed gradually
4. Monitor CFM and velocity in Fan Information panel

#### Use Cases for Manual Mode:

- Testing specific fan speeds
- Demonstrating fan effectiveness
- Baseline comparisons
- When you want consistent, predictable behavior

### Automatic Mode

In automatic mode, the controller manages fan speed:

1. Select “Automatic” from Fan Mode dropdown
2. Controller monitors all sensor pairs
3. Adjusts fan speed based on smoke levels
4. Uses PID control for smooth response

#### How Automatic Control Works:

1. **Low Sensors** determine if air quality is acceptable
  - Below threshold → Consider turning off fan
  - Above threshold → Keep fan running
2. **High Sensors** determine required fan power
  - Higher smoke concentration → Higher fan speed
  - Uses worst-case sensor reading

3. **Control Logic:**

PPM < 50:	20% fan speed (minimum)
PPM 50-150:	40% fan speed (moderate)
PPM 150-300:	70% fan speed (high)
PPM > 300:	100% fan speed (maximum)

4. **Safety Features:**

- Minimum run time of 30 seconds
- Gradual ramp up/down
- Won't turn off if low sensors detect smoke

---

## Interpreting Results

---

### Key Metrics

#### PPM (Parts Per Million)

Indicates particle concentration in air:

- **0-50:** Clean/Good air quality

- **50-150**: Moderate (noticeable but acceptable)
- **150-300**: Unhealthy (uncomfortable)
- **300+**: Very unhealthy (poor visibility)

### Air Clarity (%)

Indicates visual transmission:

- **100%**: Perfect visibility
- **85-100%**: Slight haze
- **60-85%**: Noticeable haze
- **40-60%**: Heavy smoke
- **<40%**: Very dense smoke

## Understanding the Graphs

### PPM Over Time Graph

- Shows particle concentration trends
- Multiple lines represent different sensors
- Room average shown in white
- **What to look for:**
  - Rate of PPM increase (with smokers active)
  - Rate of PPM decrease (when fan is on)
  - Differences between sensor locations

### Clarity Over Time Graph

- Mirrors PPM but from visibility perspective
- Higher is better
- **What to look for:**
  - How quickly visibility degrades
  - How quickly fan restores visibility
  - Which areas clear first

### Fan Speed Over Time Graph

- Shows fan controller behavior
- In auto mode, shows how controller responds
- **What to look for:**
  - Response time to smoke detection
  - Speed variations during clearing
  - Patterns in control strategy

## Statistics Panel

Key statistics to review:

- **Peak PPM**: Highest concentration reached
- Lower is better
- Indicates worst-case scenario
- **Average PPM**: Overall air quality
- Indicates typical conditions
- Useful for comparing configurations

- **Time to Clear:** Seconds to reach clean air
- Critical metric for fan sizing
- Lower is better
- **Current Values:** Real-time conditions
- Monitor during simulation

## Comparing Configurations

To optimize your setup:

1. **Run baseline:** Default configuration
  2. **Change one variable:**
    - Number of smokers
    - Sensor locations
    - Fan control strategy
  3. **Compare statistics:**
    - Time to clear
    - Peak PPM
    - Average PPM
  4. **Export data** for detailed analysis
- 

## Advanced Features

### Simulation Speed Control

Adjust how fast the simulation runs:

- **1.0x:** Real-time (1 second = 1 second)
- **2.0x:** Double speed
- **5.0x:** Five times faster
- **0.5x:** Half speed (for detailed observation)

#### Use Cases:

- Fast speed: Quick testing of long-term scenarios
- Slow speed: Detailed observation of smoke behavior
- Real-time: Accurate timing measurements

### Configuration Management

#### Saving Configurations

1. Set up sensors and simulation parameters
2. Click "Save Configuration" in Simulation tab
3. Choose filename and location
4. Configuration saved as JSON file

#### Saved Settings Include:

- All sensor pair locations
- Number of smokers
- Fan control mode
- Simulation speed

## Loading Configurations

1. Click “Load Configuration”
2. Select saved JSON file
3. System resets and applies saved configuration
4. Ready to run simulation

### Use Cases:

- Save different scenarios for testing
- Share configurations with colleagues
- Return to previous tests
- Document optimization process

## Data Export

### CSV Export

1. Run a simulation
2. Go to Statistics tab
3. Click “Export Data to CSV”
4. File saved to `exports/` directory

### CSV Contains:

- Timestamp for each data point
- Fan speed at each moment
- Room average PPM and clarity
- Individual sensor readings (PPM and clarity)
- Particle count

### Analysis Options:

- Import into Excel or Google Sheets
- Use Python/R for statistical analysis
- Create custom visualizations
- Generate reports

## 3D View Controls

### Navigation

- **Rotate:** Click and drag with left mouse button
- **Zoom:** Scroll mouse wheel
- **Pan:** (currently not implemented)

### View Options

Visible elements (currently always on):

- Room boundaries with floor grid
- Smoke particles (gray points)
- Sensors (green=low, red=high)
- Exhaust fan (blue circle)

### Tips for Better Viewing:

- Rotate to see smoke flow toward fan
- Zoom in to see sensor details
- Zoom out for overall room view
- Side view shows stratification clearly

## Keyboard Shortcuts

(Note: These require focus on specific widgets)

- **Space**: Start/Pause (when focused on button)
  - **+/-**: Adjust values in spinboxes
  - **Tab**: Navigate between controls
  - **Enter**: Activate focused button
- 

## Tips and Best Practices

---

### Getting Meaningful Results

#### 1. Start Simple

- Begin with 1 sensor pair
- Use medium number of smokers (24)
- Run in real-time (1x speed)

#### 2. Add Complexity Gradually

- Add more sensor pairs
- Try different locations
- Experiment with fan modes

#### 3. Test Systematically

- Change one variable at a time
- Keep notes on configurations
- Save configurations before changing

#### 4. Use Statistics

- Focus on "Time to Clear" metric
- Compare peak PPM values
- Look at sensor-to-sensor differences

## Common Scenarios

### Scenario 1: Initial Assessment

**Goal:** Understand current room performance

- Use 48 smokers (full capacity)
- Place 2-3 sensor pairs
- Run in auto mode
- Export results as baseline

### Scenario 2: Optimize Fan Control

**Goal:** Find best automatic control strategy

- Fixed smoker count (24)
- Multiple sensor locations
- Compare auto vs manual at different speeds
- Measure time to clear



## Scenario 3: Sensor Placement Study

**Goal:** Find best sensor locations

- Fixed fan speed (manual mode)
- Test different sensor positions
- Compare detection times
- Find earliest warning positions

## Troubleshooting

### Simulation Runs Slowly

- Reduce number of smokers
- Lower simulation speed
- Close other applications

### Particles Not Visible

- Zoom in to room
- Wait for particles to generate
- Check that simulation is running

### Fan Not Responding

- Check if in Manual mode
- Verify slider is not at 0%
- In Auto mode, check if sensors detect smoke

### Sensors Show No Readings

- Ensure simulation is running
- Wait for smoke to reach sensors
- Check sensor placement (inside room?)

## Appendix: Technical Details

### Physics Model Summary

The simulation uses particle-based computational fluid dynamics:

1. **Particle Generation:** 500 particles/cigar/second
2. **Forces Applied:**
  - Buoyancy (upward, temperature-based)
  - Diffusion (random dispersion)
  - Advection (fan suction)
  - Gravity (cooling particles)
3. **Boundary Conditions:** Elastic collisions with walls
4. **Removal:** Particles removed at fan or after 5 minutes

### Accuracy and Limitations

**What the Simulation Does Well:**

- General smoke movement patterns
- Relative comparisons between configurations

- Fan effectiveness demonstration
- Sensor placement optimization

**Limitations:**

- Simplified turbulence model
- No HVAC inlet modeling (yet)
- Uniform particle size
- Ideal mixing assumptions
- No temperature gradients (except buoyancy)

**For Production Use:**

- Use as design tool, not final specification
- Validate with real-world measurements
- Consider CFD analysis for critical applications
- Factor in safety margins

---

## Support and Feedback

For questions, issues, or suggestions:

- Review README.md for technical details
- Check this guide for usage questions
- Examine example configurations in `configs/` directory

---

**Version:** 1.0

**Last Updated:** December 2025